

Last name


First name

Date DD/MM/YYYY

How to complete hand outline page

Gauntlet – MCPs
to Wrist **0505**Glove to Wrist
0535Interdigital Web
Spacer **0536**Mitten (For
amputation at MCP
level) **0537**Gauntlet to Axilla **0502**Glove to Axilla **0532**Gauntlet to Elbow
0516Glove to Elbow
0534Gauntlet to Axilla with
Shoulder Attachment **0504**

CLEARLY MARK END OF GARMENT ON FINGERS



Powernet colour selection guide

Fabric & Thread: Black, Brown,
Beige, Light Beige, Purple, Navy,
Royal, Light Blue, Red, Pink,
White, Camouflage

Contrast Thread:
Orange, Hot Pink,
Lime, Yellow
Dual Stitching:
nominate 2 colours

Fabric	Thread	Qty
1	1	
2	2	
3	3	
Must provide extra colour options		
1	1	
2	2	

Hand/arm zipper locations

	Location		Full Length	Or Specify Length (cm)
	L	R		
Dorsal				
Ulnar				
Palmar				
Other:				

Comments

Garment styles

Code	L	R	Description
0505			Gauntlet - MCPs to wrist
0535			Glove to Wrist <input type="checkbox"/> Open Tips <input type="checkbox"/> Closed Tips
0536			Interdigital Web Spacer <input type="checkbox"/> Thumb <input type="checkbox"/> No Thumb
0537			Mitten to Wrist (amputee)
0502			Gauntlet to Axilla
0532			Glove to Axilla <input type="checkbox"/> Open Tips <input type="checkbox"/> Closed Tips
0516			Gauntlet to Elbow
0534			Glove to Elbow <input type="checkbox"/> Open Tips <input type="checkbox"/> Closed Tips
0504			Gauntlet with Shoulder Attachment
0025			Individual Finger Stall <input type="checkbox"/> Open Tips <input type="checkbox"/> Closed Tips <input type="checkbox"/> Wrist Band

Options and modifications

Code	L	R	Description
			Seam-free thenar eminence
0021			Reinforced Palm (Powernet)
1183			Palm Grip <input type="checkbox"/> Silicone <input type="checkbox"/> Suede
1188			Positional Reinforcement (indicate on hand outline)
1169			Slant Inserts
0027			Padding - Soft <input type="checkbox"/> Pocket <input type="checkbox"/> Attached (Indicate on TBSA Map or hand trace).
0027			Padding - Velfoam <input type="checkbox"/> Pocket <input type="checkbox"/> Attached (Indicate on TBSA Map or hand trace)
1202			Motif
SBE			Silicone Backed Elastic
1190			Anterior Elbow Insert
0000			Left Elbow Contracture Seamdegrees
0000			Right Elbow Contracture Seamdegrees
GCCINSERT			Contrast Colour Inserts (specify 3 choices) 1..... 2..... 3.....
0021			Lining-Palm
1167			Lining-Inside Elbow <input type="checkbox"/> Satin <input type="checkbox"/> Cotton
1168			Lining-Full Elbow <input type="checkbox"/> Satin <input type="checkbox"/> Cotton
1167B			Lining-Posterior Elbow <input type="checkbox"/> Satin <input type="checkbox"/> Cotton
1188			Lining (specify location) <input type="checkbox"/> Satin <input type="checkbox"/> Cotton
1195			Full Lined Garment <input type="checkbox"/> Soft Satin <input type="checkbox"/> Cotton
			SilonTEX® lining – indicate location and size on either hand outline, TBSA map or printed photo
1164			Zippers (20cm or less)
1165			Zipper (over 20cm)
1172A			Zipper Loop (leather)
ZCT			Zipper Closure Velcro® Tab (top of zipper)
1163B			Zipper Fastening Aids (along length of zipper)
0000			Zipper Lining <input type="checkbox"/> Satin <input type="checkbox"/> Elastic
0027			Padded Zipper Lining

Glove, Gauntlet

Measurement Form – Page 2 of 3

Patient details (Please print in black with CAPITAL letters)

Last name

First name

Date

DD/MM/YYYY



Desired finger lengths

White boxes are lengths and grey boxes are circumferences

3cm past wrist

6cm past wrist

For garments finishing above elbow measure length from wrist to end of garment

This is a **horizontal** measure around the MCP.

Arm circumferences

Pleat		Pleat		
Left (cm/mm)		Wrist End	Right (cm/mm)	
		-3		
		-1 1/2		
		0		
		1 1/2		
		3		
		4 1/2		
		6		
		7 1/2		
		Elbow 9		
		10 1/2		
		12		
		13 1/2		
		15		
		16 1/2		
		18		
		19 1/2		
Pleat		Axilla End	Pleat	

Desired finger lengths

White boxes are lengths and grey boxes are circumferences

3cm past wrist

6cm past wrist

For garments finishing above elbow measure length from wrist to end of garment

This is a **horizontal** measure around the MCP.

Shoulder attachment measurements

1. Distance last arm tape to inside edge of bra strap	2. Top of shoulder, circumferentially under opposite breast	3. Top of shoulder, circumferentially under opposite axilla	4. Top of shoulder, diagonal to waist
Bra Loop (cm)	Female Body Strap (cm)	Male/Child's Body Strap (cm)	Waist Attachment (cm)
1	2	3	4
2a, 3a, 4a: Distance last arm tape to base of neck	2a	3a	4a

Glove, Gauntlet

Measurement Form – Page 3 of 3

Last name	First name
-----------	------------

First name

Date DD/MM/YYYY




Mark clear and accurate web heights

Please keep arm and middle finger in line

All measurements taken with no tension and in centimetres only.

Design options



Gloves & gauntlets definition, hints and tips

Gauntlet measurements required: palm, thumb, wrist and any arm measurements needed. The hand outline must be completed.

The hand drawing must be aligned as per markings, middle finger perpendicular to the wrist, and palm down. The fingers and palm should be flat against the paper. The important points to mark exactly are the web spaces, wrist and finishing point glove.

If fingers are contracted measure from the web space along the side of the fingers and follow the curve to the desired length of each finger. **A glove to wrist** may extend up to tape 3.

Finger Circumferences: Take with a JOBSKIN finger tape and measure in skin contact - not tightly.

Finger Lengths: Can be taken with the JOBSKIN Handy-card.

Open Tips: Measure only the length desired from the Finger Web Space (palmar aspect).

Slant Inserts: Enable a snug fit on the dorsal surface and give extra pressure in the web spaces.




Use the finger tape to measure finger circumferences of hand. Use the **purple** measuring tape for the arm.

Web Spacers: Are designed to give extra pressure in the web spaces and are worn over gloves. They can be ordered with or without a thumb piece.

Zippers: May be used to allow for inserts, e.g. silicone gel sheets.

Arm measuring tips

With the arm straight and horizontal, proceed measuring using a **Purple** JOBSKIN arm tape.




For a Full Length Sleeve begin by securing tape 9 directly around the elbow. The last tape should fall just below the wrist bone (distal to styloid process). Pleating at the spine occurs ONLY at the wrist and axilla if required.

For a Forearm Sleeve begin tape at wrist and pleat at proximal end if required.


Pleat instructions

When pleating the last tape, measure the distance between the pleated tape and its neighbour from mid point to mid point (see diagram).



Reading the tapes

Always read along the **straight edge** and in direction of arrows as indicated below.



Email or return forms to:

Unit 1, Level 1, 100 Station Street
Nunawading Victoria 3131, Australia
T (AU): 1800 772 577
T (NZ): 0800 765 627
T (Int'l): +61 3 9915 8000
E: customer.service@jobskin.com
W: www.jobskin.com

Garment returns:

Unit 1, Level 1, 100 Station Street
Nunawading Victoria 3131, Australia